Bot Commands

Every @hafizebot command, grouped, with the range and meaning of each autotrader setting.

October 2026



REFERENCE

How commands work

Everything happens in a chat with **@hafizebot** on Telegram. A command is a word starting with a slash, such as `/start`; the menu buttons send the same commands for you. Commands are grouped by who can use them: anyone, VIP members, or members with autotrading enabled.

- Command names are case-insensitive: `/setLeverage` and `/setleverage` are the same command.
- When the bot is waiting for a value (for example after `/setleverage`), send the value as a plain message, or `/cancel` to stop.
- `/help` lists the commands available to your account right now; `/summary` shows all your autotrader settings in one message.
- You need a Telegram username; the bot refuses to work without one.

Getting started

Command	What it does
`/start`	Show the main menu
`/help`	List the commands you can use
`/status`	Show your account status
`/setup`	Your setup checklist and the next step
`/explain`	Pick a setting to see what it does, your value and the default
`/faq`	Answers to common questions, by topic
`/trial`	Start the free 3-day VIP trial; autotrading during it is capped at 10 USDT per trade and 3 open positions
`/language`	Choose your language
`/signals`	Get the free signals channel link
`/guides`	Download the member guides (this document and the others)
`/results`	Download the monthly order reports
`/support`	Send feedback to the team
`/cancel`	Cancel whatever the bot is waiting for

REFERENCE

VIP and payments

VIP is paid in USDT on one of the networks `/join` offers: BEP20 (BSC), TRC20 (Tron), Solana or TON. A deposit credits your balance; a plan is then bought from that balance.

Command	What it does
`/join`	How to become a VIP member: pick a network for the deposit address, plus the current prices
`/plans`	VIP tiers and pricing
`/vipinfo`	What VIP membership includes
`/howtowithdraw`	Screen-by-screen walkthrough of sending USDT from Binance
`/pay <txid>`	Verify a USDT transfer and credit it to your balance (`/deposit` is the same command). Accepts the transaction ID your wallet shows (on BEP20 it starts with 0x) or a Binance internal-transfer number.
`/balance`	Show your USDT balance and the plans it covers
`/buy <plan>`	Buy or extend VIP from your balance: `tier1`, `tier2`, `tier3`, `tier1 annual`, `tier2 annual`, `tier3 annual`. Without a plan it lists the ones your balance covers.
`/renew`	How to renew your membership
`/subscribe`	Auto-renew from your balance when VIP is within 3 days of expiry; `/subscribe off` disables it
`/status`	When your VIP membership expires
`/coupon <code>`	Redeem a coupon code for VIP
`/invite <username>`	Name the VIP member who invited you — before you buy. You both get one extra week.
`/autotrade`	Switch on auto-trading and add your Binance key (immediate for VIP members)

Prices: Tier 1 is 50 USDT a month or 500 USDT a year; Tier 2 is 100 USDT a month or 1,000 USDT a year; Tier 3 is 200 USDT a month or 2,000 USDT a year. Annual plans include two free months.

REFERENCE

Autotrader control

These commands need autotrading enabled on your account: `/autotrade` switches it on at once for VIP members. Changes apply immediately to the next signal.

Command	What it does
`/on`	Turn autotrading on. It first checks your Binance key: if Binance refuses the key, or Enable Futures is not ticked on it, autotrading stays off and the bot tells you why.
`/off`	Turn autotrading off — open positions and their orders are left as they are
`/settings`	Open the settings menu
`/summary`	Show all your autotrader settings in one message
`/bancoin, /unbancoin`	Add or remove coins the bot must never trade, e.g. `/bancoin BTCUSDT ETHUSDT`
`/bansignal, /unbansignal`	Add or remove signal elements the bot must never trade (Tier 2). `/bansignal` on its own shows buttons; a tap bans or unbans.
`/bangroup, /unbangroup`	Add or remove whole Binance groups the bot must never trade, e.g. `/bangroup Meme` (Tier 2). `/bangroup` on its own shows buttons; a tap bans or unbans.
`/banlist`	Show your banned coins, signals and groups
`/allowrepeatingsignals`	Allow (yes) or block (no) entering a new signal on a coin you already hold
`/combinetakeprofits`	Merge take-profit orders into one combined order when possible (yes/no)
`/setdelistingclose`	Close before a delisting (on or off, default off). On: if Binance announces it will delist a coin you hold, the bot closes your position with a market order shortly before settlement and cancels its take-profit and stop. Off: the position stays open until you close it or Binance settles it at its own price. Either way the bot opens no new trades on a coin Binance is delisting.

Settings

Every setting has a `/set…` command that changes it and a `/my…` command that shows the current value. The bot rejects values outside the range for your tier.

Setting	Set / show	Range or options	Meaning
Leverage	`/setleverage` `/myleverage`	1 – 20	Leverage for new positions. On Tier 2 and 3 a trade rule can give one kind of trade another leverage. An add to a coin you already hold keeps that coin's leverage. Binance's own maximum for the coin applies on top.

Setting	Set / show	Range or options	Meaning
Position size	`/setpositionsize` `/mypositionsize`	5 – 50 USDT (Tier 1) 5 – 10,000 USDT (Tier 2) 5 – 50,000 USDT (Tier 3)	USDT committed per entry; the position's notional value is size × leverage. It is the most one trade ever uses: Smart sizing (Tier 2 and 3) can use a share of it, never less than 5 USDT. The free trial caps it at 10 USDT.
Position limit	`/setpositionlimit` `/mypositionlimit`	1 – 10 (Tier 1) 1 – 100 (Tier 2) 1 – 500 (Tier 3)	Maximum open positions at once, counting positions you opened by hand. New coins are skipped once the limit is reached. The free trial allows 3.
Minimum signal strength	`/setminstrength` `/myminstrength`	0 – 5	Only signals rated at or above this value are entered. 0 = no filter. Example: 3 enters signals rated 3, 4 and 5.
Stop loss	`/setstoploss` `/mystoploss`	0 – 90 %	Stop distance from entry, **without leverage**. 0 = no stop order. Example: 5 with 10x leverage stops at a 50% loss on the margin. On isolated margin the stop must sit inside the liquidation distance: at most 35% at 2x, 14% at 5x, 7% at 10x, 3.5% at 20x.
Stop type	`/setstoptype` `/mystoptype`	OFF · SINGLE · COMBINED	OFF turns off your own stop; a trade rule's stop is still placed. SINGLE places one stop per entry, for that entry's quantity, from that entry's price; earlier entries keep theirs. COMBINED replaces them with one stop for the whole position, from the average entry.
Take-profit type	`/settakeprofittype` `/mytakeprofittype`	LIMIT · TRAILING	LIMIT places a reduce-only limit order at the target. TRAILING places a trailing stop that activates only once the price moves beyond the target, then follows it. If the price touches the target and turns back, the position stays open.
Position side	`/setpositionside` `/mypositionside`	LONGONLY · SHORTONLY · BOTH	Which signal directions the bot may enter.
Margin type	`/setmargintype` `/mymargintype`	ISOLATED · CROSSED	Binance margin mode used for the bot's positions.
Same-coin gap	`/setdifference` `/mydifference`	0 – 100 %, default 3	A new signal on a coin you hold is taken only if its entry is more than this far from your last entry on the coin: above it for a short, below it for a long. 0 allows any spacing.
Coin pause	`/setcoinpause` `/mycoinpause`	0 – 1440 min, default 0	Minutes the bot waits before entering a coin again after a position on it closes. 0 = no pause.

Setting	Set / show	Range or options	Meaning
Minimum 24h volume (Tier 2+)	`/setminvolume` `/myminvolume`	0 – 10B USDT, e.g. 5M; 0 = off	Coins whose 24h volume is under it are skipped, and so are coins whose volume is unknown just now.
Minimum coin age (Tier 2+)	`/setmincoinage` `/mymincoinage`	0 – 365 days; 0 = off	Coins listed on Binance Futures more recently than this are skipped, and so are coins whose listing date is unknown.
Trade notices	`/settradenotices` `/mytradenotices`	ALL · CLOSES · OFF, default ALL	Which trade messages you get. Trading is the same either way.

Tier 3 limits

Optional risk settings for Tier 3 members. Each starts off (0, or off) and applies from the next signal; the re-base step starts at 25% and matters only once your size or limit follows your wallet. On a lower plan the bot answers with the plan you need. They are tools with trade-offs, not improvements to the signals: in our tests on past signals the loss limits, the entry cap and the 24-hour move conditions often gave up more than they saved, the maximum hold time protected in sharp falls but cost return in rising markets, and the funding pause gave up a little return on its own; the break-even stop has not been tested yet. Past results guarantee nothing.

Setting	Set / show	Range or options	Meaning
Daily loss limit	`/setdailylosslimit` `/mydailylosslimit`	0 – 100 % of the wallet; 0 = off	Once your realised loss since 00:00 UTC reaches this share of your futures wallet at 00:00 UTC, the bot opens no new coin and adds to none until 00:00 UTC. Closing orders, take-profits and stops are never held back.
Weekly loss limit	`/setweeklylosslimit` `/myweeklylosslimit`	0 – 100 %; 0 = off	The same over the UTC week, from Monday 00:00.
Maximum entries	`/setmaxentries` `/mymaxentries`	0 – 50 per coin; 0 = off	The most entries on one coin while its position is open, the first included: 1 means no adds.
Maximum hold time	`/setmaxhold` `/mymaxhold`	0 – 720 hours; 0 = off	A position the bot opened that has not reached its target after this many hours is closed with a market order, and its take-profit and stop are cancelled. Positions you opened yourself are never touched.
Break-even stop	`/setbreakeven` `/mybreakeven`	0.2 – 50 % in profit; 0 or off = off	Once a position the bot opened is this far in profit from its average entry, its stop moves to the break-even price (fees included) and the bot adds nothing more to that coin until the position closes. The new stop closes the whole position on that coin, a part you added by hand included. Take-profits stay as they are; positions you opened yourself are never touched.

Setting	Set / show	Range or options	Meaning
Long skip after a rise	`/setlongskipup` `/mylongskipup`	0 – 1,000 %; 0 = off	Skip a new long on a coin that rose this much or more over the last 24 hours.
Long skip after a fall	`/setlongskipdown` `/mylongskipdown`	0 – 1,000 %; 0 = off	Skip a new long on a coin that fell this much or more over the last 24 hours.
Short skip after a fall	`/setshortskipdown` `/myshortskipdown`	0 – 1,000 %; 0 = off	Skip a new short on a coin that fell this much or more over the last 24 hours.
Short skip after a rise	`/setshortskipup` `/myshortskipup`	0 – 1,000 %; 0 = off	Skip a new short on a coin that rose this much or more over the last 24 hours.
Maximum 24-hour range	`/setmaxdayrange` `/mymaxdayrange`	0 – 1,000 %; 0 = off	Skip a new coin whose range from its 24-hour low to its high is this share of the low or more: between 100 and 130 is 30%.
Minimum 24-hour trades	`/setmintrades` `/mymintrades`	0 – 100,000,000 trades, e.g. 50K; 0 = off	Skip a new coin that had fewer trades than this over the last 24 hours.
Long skip above the 24-hour average	`/setlongskipaboveavg` `/mylongskipaboveavg`	0 – 1,000 %; 0 = off	Skip a new long when the price is this much or more above the coin's 24-hour average price.
Short skip below the 24-hour average	`/setshortskipbelowavg` `/myshortskipbelowavg`	0 – 1,000 %; 0 = off	Skip a new short when the price is this much or more below the coin's 24-hour average price.
Funding pause	`/setfundingpause` `/myfundingpause`	on · off, default off	On a UTC day when funding across the market is strongly negative, the bot opens no new trades and adds to no coin until the next 00:00 UTC. On a day the reading is not available, it trades as usual.
Minimum target distance	`/setmintarget` `/mymintarget`	0 – 100 %; 0 = off	Skip a signal whose target is less than this far from its entry (the exact distance; the message shows it rounded down as "Profit"), for a new coin and for an add. A signal without a target is skipped while it is on.
BTC guard	`/setbtcguard /mybtcguard`	0 – 100 % for each of four values; off turns all four off	While BTC has fallen this much or more over the last hour, or over 24 hours, the bot opens no new long and adds to no long; after a rise, the same for shorts. Send /setbtcguard alone for the exact form. If BTC's move cannot be read, that side waits.

Setting	Set / show	Range or options	Meaning
Drawdown brake	`/setdrawdownbrake 10 50` `/mydrawdownbrake`	1 – 90 % below the peak, then 10 – 100 % of the size; off turns it off	Once your futures wallet is that far below its peak, new entries and adds use that share of their usual size, never less than 5 USDT, until your wallet is back within 2% of the peak.
No long adds while braked	`/setnolongaddsindrawdown` `/summary`	on · off, default off	While the drawdown brake is on, the bot adds nothing to the longs you hold; shorts and new coins are not affected.
Size from your wallet	`/setpositionsize 0.35%` `/mypositionsize`	0.1 – 5 % of the wallet; 0% = off	Your size as a share of your futures wallet. The bot sets your size in USDT from it, and again each time your wallet has moved your re-base step up or down; never below 5 USDT, never above your plan's maximum. A size in USDT turns it off.
Limit from your wallet	`/setpositionlimit per 125 8-16` `/mypositionlimit`	25 – 10,000 USDT per coin; range optional; per off = off	One coin per that many USDT of your futures wallet, within your own fewest and most coins and your plan's maximum, set with your size. Coins already open are never closed for it. A plain limit turns it off.
Re-base step	`/setrebasestep` `/myrebasestep`	10 – 50 %, default 25	How far your wallet moves, up or down, from the last change before your size and limit follow it.

The 24-hour conditions use Binance's own figures for the coin and look at new coins only; an add to a coin you hold is not affected. If a figure a setting needs cannot be read, the new coin is skipped. While your size or limit follows your wallet, size × limit may use at most 60% of your futures wallet: a larger value is not saved, and the bot skips an entry that would take the margin of your open positions past it. `/summary` shows them all and `/explain` says what each does.

REFERENCE

Settings explained

Position size and leverage

Position size is the margin in USDT the bot commits to each entry; leverage multiplies it into the position's notional value. A 20 USDT size at 10x opens a 200 USDT position. The stop-loss percentage is measured on the unleveraged price move, so with leverage the loss on your margin is that percentage times the leverage. On Tier 2 and 3, Smart sizing can use only a share of the size for some kinds of trade, and a trade rule can give a kind of trade its own leverage (see below).

Size from your wallet (Tier 3)

On Tier 3 your position size can be a share of your futures wallet: `/setpositionsize 0.35%` (0.1% to 5%; `0%` turns it off). The bot then sets your size in USDT from your margin balance and checks it every 15 minutes: each time your wallet has moved your re-base step (`/setrebasestep`, 25% unless you change it, 10 to 50%) up or down from where it stood at the last change, it sets your size again and sends you one message. So your size grows and shrinks with your wallet, in steps and both ways: never below 5 USDT and never above your plan's maximum. This sets how much each trade puts at risk as your wallet changes; it does not choose trades and does not make the signals more profitable. Sending a size in USDT turns it off. `/mypositionsize` shows the share and the wallet your size was last set from.

Limit from your wallet (Tier 3)

On Tier 3 your position limit can follow your futures wallet too: `/setpositionlimit per 125 8-16` keeps one coin per 125 USDT of your wallet, never fewer than 8 and never more than 16 coins (and never more than your plan allows). Any amount from 25 to 10,000 USDT per coin works, and the range is optional: without one the bot keeps the range you saved, or one coin at least and your current limit at most. The bot sets the limit with your size, at the same re-base step and in the same message, so a smaller wallet holds fewer coins and a larger one more. Coins already open are never closed because the limit went down; new signals wait instead. You can use it with or without a share of the wallet for the size. It is a risk setting: it keeps the number of open coins in step with your wallet and does not make the signals more profitable. `/setpositionlimit per off` or a plain number turns it off.

Drawdown brake (Tier 3)

On Tier 3 the bot can trade a smaller size while your account is well below its best: `/setdrawdownbrake 10 50` halves your size in a drawdown until the wallet recovers. The bot keeps the peak of your futures wallet from the moment you set the brake and checks it every 15 minutes. Once your wallet is the first number's percent or more below that peak (1 to 90), every new entry and add uses the second number's percent of its usual size (10 to 100), never less than 5 USDT, until your wallet is back within 2% of the peak. Open positions are never touched, and you get one message when it starts and one when it ends. With `/setnolongaddsindrawdown on` the bot also adds nothing to the longs you hold while the brake is on. Money you move out of the futures wallet counts as a drop: send the command again to start the peak afresh. It is a survival setting: it may reduce losses in a slide and costs return in a recovery, and it does not make the signals more profitable. `/mydrawdownbrake` shows where your wallet stands; `/setdrawdownbrake off` turns it off.

Position limit

The limit counts every open position on the account, including the ones you opened yourself. When the limit is reached, the bot still adds to a coin it already holds (if repeating signals are allowed and the same-coin gap is respected) but does not open a new coin. In a volatile market the model can fire many signals in a short time; the limit is what keeps a burst of signals from committing your whole wallet. **Set it.** When you change your position size or limit, the bot reads your futures wallet and warns you if size × limit is more than 60% of it, and the value is saved. While your size or limit follows your wallet (Tier 3), more than that is not saved, and the bot skips an entry that would take the margin of your open positions past it.

Stop loss and stop type

With a stop percentage above 0 and a stop type other than OFF, the bot places a stop-market order right after the entry fills. SINGLE places one stop per entry, for that entry's quantity, from that entry's price; earlier entries keep their own stops, and a manual add-on you opened by hand is never closed by the bot's stop. COMBINED cancels the existing stops and places one stop for the whole position, measured from the average entry. With the stop type OFF your own stop is turned off, but a trade rule's stop for that kind of trade is still placed.

The stop can be set from 0 to 90%. On isolated margin it must also sit inside the liquidation distance, or Binance liquidates the position before the stop is reached: at most 35% at 2x, 14% at 5x, 7% at 10x and 3.5% at 20x. The bot refuses a wider stop and tells you the largest one your leverage allows.

The stop is a price move from your entry, not a share of your margin. What it costs is the stop times your leverage, as a share of the trade's margin: 10% at 2x is 20% of the margin, and 50% at 3x is 150%, more than all of it. To lose at most half the margin at 5x, set a 10% stop, not 50. On cross margin a stop that costs more than the whole margin is saved with a warning, and the rest of a loss comes from your futures balance. `/setstoploss`, `/mystoploss` and `/summary` show this share for your own leverage.

Take-profit type

LIMIT is the default: a reduce-only limit order at the signal's target, which closes the position when the target trades. TRAILING places a trailing stop that activates only once the price moves beyond the target and then follows it, so part of a move past the target can be kept. If the price touches the target and turns back, the trailing stop never activates and the position stays open. `/combinetakeprofits yes` merges take-profit orders on the same coin into one order when possible.

Repeating signals and the same-coin gap

A second signal on a coin you already hold adds to the existing position, and an add keeps the leverage the coin already has: neither a trade rule nor a later `/setleverage` moves an open position's leverage. `/allowrepeatingsignals no` blocks adds entirely. Even when allowed, the same-coin gap (default 3%) applies: a short is added only if its entry is more than the gap above your last entry on that coin, a long only if it is more than the gap below it. The bot only acts when a new signal fires; it never buys a dip or averages down because price moved.

Coin pause

`/setcoinpause` sets how many minutes the bot waits before entering a coin again after a position on it closes, whether by target, stop or by hand. 0 (the default) means no pause; the longest is 1440 minutes, a full day.

Trade notices

`/settradenotices` chooses which trade messages you get. ALL (the default) sends every fill; CLOSES sends only the fills that close a position, with their result; OFF sends none. Trading is the same either way, and `/myresults` and `/lastsignals` always show what happened.

Smart sizing, trade rules and take-profit distance (Tier 2 and 3)

Command	What it does
`/smartsizing`	Shows your shares and what they do to your next trades
`/setsize longs 50`	Longs use half your position size. Also `/setsize strength 2 50`, `/setsize Meme 50` (a Binance group), `/setsize reset`.
`/traderules`	Shows your rules and what they do to your next trades
`/setrule shorts stop 30`	Shorts get a 30% stop, whatever `/setstoploss` says; `stop none` means no stop for that kind
`/setrule shorts gap 3`	Shorts get a 3% same-coin gap
`/setrule shorts strength 3 off`	The bot skips shorts of strength 3; `on` trades that kind again
`/setrule shorts max 3`	A cap: at most three open coins of that kind; `/setmaxlongs 5` and `/setmaxshorts 3` set a side's cap, `/mymaxlongs` and `/mymaxshorts` show it
`/setrule coin BTC leverage 2`	New BTC positions open at 2x
`/setrule volume under 10M USDT max 3`	At most three open coins with a 24h volume under 10M USDT
`/setrule shorts age under 30 off`	The bot skips shorts on coins listed less than 30 days ago
`/setrule reset`	Clears every rule; `/setrule shorts reset` clears one
`/takeprofitdistance`	Shows your take-profit distances
`/settakeprofitdistance shorts 120`	Sets where the take-profit of one kind of trade sits

Smart sizing sets how much of your position size each kind of trade uses: longs or shorts, a strength, a signal name or a Binance group. 100% is the full size and 0% skips that kind of trade. Shares go in steps of 5 and they multiply: with longs at 50 and strength 2 at 50, a long of strength 2 uses 25%. For a coin in several groups the smallest share counts. Your position size is always the most one trade uses, and a trade that is not skipped never uses less than 5 USDT.

Trade rules give one kind of trade its own stop, same-coin gap, on/off switch, cap (the most coins of that kind open at once) or leverage. A kind can be longs or shorts, a strength, a signal name, a Binance group, one coin, a 24h-volume band (under 10M, 10–50M, 50–200M, over 200M USDT) or a coin-age band (under 30, 30–90, 90–365, over 365 days). The most specific rule wins and anything a rule does not set uses your normal settings. You can keep up to 64 rules. A rule's stop goes from 0 to 90% and its gap from 0 to 100%; it follows the same liquidation check as your own stop, and it is placed even when the stop type is OFF. A cap stops the bot opening a new coin of that kind once that many are open; it never blocks an add. A coin whose volume or listing date is unknown is in no band, so band rules leave it to your other rules.

Take-profit distance sets where your take-profit sits compared with the signal's target: 100% is at the target, 120% puts it 1.2 times as far from your entry, 80% takes profit sooner. It goes from 50% to 300% in steps of 10. Only your own order moves; the signal and its published result keep the signal's target. A farther take-profit is reached less often and a nearer one closes winners earlier: neither is better for everyone.

`/summary` shows all three, and `/lastsignals` says when a signal was skipped or sized by them. Nothing applies until you set it.

Minimum volume and coin age (Tier 2 and 3)

`/setminvolume` skips coins whose 24h trading volume is under your minimum (write it as `5M`, `500K` or `1.5B`); `/setmincoinage` skips coins listed on Binance Futures fewer than that many days ago. 0 turns each off. When a minimum is set and the bot cannot read the coin's volume or listing date just now, it skips the coin rather than guess.

Close before a delisting

When Binance announces that it will delist a coin, the bot opens no new trades on it. `/setdelistingclose on` also has the bot close your position on that coin with a market order shortly before Binance's settlement and cancel its take-profit and stop. Off (the default), the position stays open until you close it or Binance settles it at its own price.

Free trial limits

During the free 3-day trial (`/trial`), autotrading is capped at 10 USDT of margin per trade and 3 open positions at once. The caps hold whatever the settings say.

Where a new account starts

Setting	Starts at	Change with
Position size	5 USDT	/setpositionsize
Leverage	2x	/setleverage
Margin type	Isolated	/setmargintype
Position limit	3	/setpositionlimit
Minimum signal strength	5, the highest-rated signals only	/setminstrength
Stop loss	10%, SINGLE (one stop per entry)	/setstoploss, /setstoptype
Direction	long and short	/setpositionside
Take-profit	LIMIT at the target	/settakeprofittype
Same-coin gap	3%	/setdifference
Banned group	TradFi	/bangroup (Tier 2+)

These starting values are for safer first weeks, not for more profit: only the highest-rated signals, a small size and a close stop, so a new account trades less often and each losing trade costs little. Accounts set up earlier keep the settings they have; `/summary` shows yours. These are starting values, not advice.

Banlists

`/bancoin` keeps the bot away from coins you do not want to trade, whatever the signal. Tier 2 members can also `/bansignal` a whole element, which is the way to filter by signal type, and `/bangroup` a whole Binance group such as TradFi (tokenized stocks, commodities and indices), Meme or Layer-2. Send `/bansignal` or `/bangroup` on its own to get buttons; a tap bans or unbans. New accounts start with TradFi banned. `/banlist` shows all three lists.

Reports and guides

Command	What it does
`/myresults`	What the bot's own trades did on your account in the last 30 days, fees and liquidations included. Trades you placed yourself are not counted.
`/lastsignals`	Each recent signal and why the bot took it or skipped it
`/today`	What the bot did on your account in the last 24 hours
`/results`	Download a monthly order report (also on hafizebot.com/reports)
`/guides`	Download the member guides

Support

- Telegram: questions go to **@Hafizebotadmin**, usually answered within a day; `/support` in @hafizebot sends feedback to the team.
- Email: **hello@hafizebot.com** for payment issues; include your Telegram username and the transaction ID.
- Live record: hafizebot.com/performance.

> RISK DISCLOSURE
> Cryptocurrency futures trading carries a high risk of loss and is not suitable for every investor. Signals and autotrading are tools, not financial advice. Past performance does not guarantee future results. Never trade with money you cannot afford to lose.

HafizeBot · Telegram: @hafizebot · hello@hafizebot.com · hafizebot.com